

Sistemas & Informática

Brasília - DF

www.softsol.com.br suporte@softsol.com.br

Configurando o Acesso Remoto ao Servidor Linux

Após clicar no link, aparecerá uma mensagem se deseja <u>salvar</u> ou <u>executar</u> o arquivo SoftSol.exe, selecione a opção de salvar e grave-o na Área de Trabalho (Desktop).

Feito a gravação, dê click duplo no ícone SoftSol.exe na Área de Trabalho e logo aparecerá a seguinte tela:

Category:		
🖃 Session	Basic options for your Pu	ITTY session
Logging	Specify the destination you want to	o connect to
lerminal	Host Name (or IP address)	Port
Rell	1	22
Features	Connection type: Raw O Telnet O Rlogin ③ SSH O Serial	
Appearance Behaviour Translation Selection	Load, save or delete a stored session Saved Sessions	
Colours Connection Data Proxy Telnet Rlogin	Default Settings	Load Save Delete
i⊞ SSH Serial	Close window on exit:	nly on clean exit

Em seguida, click no **Keyboard** do sub-menu: **Terminal** do menu: **Category** (lado esquerdo), e marque a opção **Control-H** (lado direito em amarelo), conforme a figura abaixo:

🚍 Session
 Session Logging Terminal Bell Features Window Appearance Behaviour Translation Selection Colours Connection Data Proxy Telnet Rlogin SSH Serial

OFTSOL Linux Sistemas & Informática

Brasília - DF

www.softsol.com.br suporte@softsol.com.br

Click no sub-menu: Features (lado esquerdo), e marque a opção Disable application keypad mode (lado direito em amarelo), veja:

 Session Logging Terminal Keyboard Bell Features Window Appearance Behaviour Translation Selection Colours Connection Data Proxy Telnet Rlogin SSH Serial 	Category:	
	 Session Logging Terminal Keyboard Bell Features Window Appearance Behaviour Translation Selection Colours Connection Data Proxy Telnet Rlogin SSH Serial 	Enabling and disabling advanced terminal features Disable application cursor keys mode Disable application keypad mode Disable term-style mouse reporting Disable remote-controlled terminal resizing Disable switching to alternate terminal screen Disable remote-controlled window title changing Response to remote title query (SECURITY): None Image: Empty string Disable destructive backspace on server sending ^? Disable rabic text shaping Disable bidirectional text display

Click no sub-menu: Window (lado esquerdo), e marque a opção Change font size only when maximised (lado direito em amarelo):

🗐 Session	Options con	trolling PuTTY's window
Logging Terminal Keyboard	Set the size of the wind Rows	dow Columns
Features Features Appearance Behaviour Translation Selection Colours Colours Colours For Connection Data Proxy Telnet Riogin SSH Serial	When window is resize O Change the numbe O Change the size of O Change font size of O Forbid resizing com Control the scrollback	ed: er of rows and columns the font nly when maximised apletely in th <mark>e window</mark>
	Lines of scrollback Display scrollbar Display scrollbar in Reset scrollback of Reset scrollback of Push erased text in	200 full screen mode n keypress n display activity ito scrollback

SOFTSOL Linux Sistemas & Informática Brasília - DF www.softsol.com.br suporte@softsol.com.br

Click no sub-menu: **Session** (lado esquerdo), e marque a opção **Telnet** (lado direito), bem no final marque **Always** (lado direito), dê <u>um click</u> em **Default Settings** e logo em seguida, click no botão **Save**:

Category:	
 Session Logging Terminal Keyboard Bell Features Window Appearance Behaviour Translation Selection Colours Connection Data Proxy Telnet Rlogin SSH Serial 	Basic options for your PuTTY session Specify the destination you want to connect to Host Name (or IP address) Port 23 Connection type: Raw Telnet Rlogin SSH Seria Load, save or delete a stored session Saved Sessions Default Settings Load Save Delete
	Close window on exit: Always Never Only on clean exit

E para finalizar, digite no campo **Host Name (or IP address)** o seguinte: 192.168.1.2 , e no Campo **Saved Session** digite: SoftSol Linux , clicando em seguida o botão **Save** , conforme a figura.

E Session	Basic options for your PUTTY session	
□ Logging □ Terminal □ Keyboard □ Bell	Specify the destination you want to connect to Host Name (or IP address) Port 192.168.1.2 23	
Features Features Window Behaviour Translation Selection Colours Colours Connection Data Proxy Telnet Rlogin	Connection type: Raw Telnet Rlogin SSH Sectors Load, save or delete a stored session Saved Sessions SoftSol Linux Default Settings Load Save Default Settings	rial J e
⊡ SSH Serial	Close window on exit:	

Pronto, para acessar apenas dê click duplo no nome SoftSol Linux (abaixo de **Default Settings**) e digitar o usuário vendas??? no login.